



Technical Support Knowledge Base


eLine TRIBRID Recorders

Motion Detection and recording configuration



From Live screen:

- Right click and choose Main Menu
- Login
- Click on the CAMERA icon [bottom row]
- Click on ENCODE [Left column]
- Select the recording resolution and frame rates desired for each camera
- Click APPLY and SAVE when all cameras have been adjusted
- Click on EVENT icon [bottom row]
- **IMPORTANT** DO NOT "COPY TO ALL" WITHIN THIS MENU. DOING SO WILL SET ALL CHANNELS TO RECORD ON CH 1**
- Click on DETECT/VIDEO DETECT
- ENABLE motion for each channel
- Click region SETUP (do this for all channels)
To select a region - left click and drag across screen to turn blocks red
RED = Motion
CLEAR = NO motion
- Right click to exit region settings
- Click APPLY and SAVE
- Click on the STORAGE icon [bottom row]
- Click SCHEDULE
- Click on the COG WHEEL icon [right side]





Technical Support Knowledge Base eLine TRIBRID Recorders Motion Detection and recording configuration

- Deselect REGULAR and SELECT MD for Period 1
- Select ALL for all days, click SAVE
- Click COPY and select ALL for all cameras
- Click APPLY
- Click RECORD [Left column]
- Select ALL button listed under MAIN STREAM SCHEDULE (or it also may say AUTO)
- Click APPLY/OK
- Right-Click to exit the Menu



A green camera / red running men icons appear at the top right corner of each camera if motion is detecting. THERE ARE NO ICONS visible if motion is not being detected.

Green camera = Recording to the HDD

Red running men = Motion is enabled and working